



Dialog Tag Language
Guide and Reference
Technical Upgrade

Operating System/2
Programming Tools
and Information
Version 1.2/1.3

91F8685



First Edition (December 1990)

The following paragraph does not apply to the United Kingdom or any country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This publication could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time.

It is possible that this publication may contain reference to, or information about, IBM products (machines and programs), programming, or services that are not announced in your country. Such references or information must not be construed to mean that IBM intends to announce such IBM products, programming, or services in your country.

Requests for technical information about IBM products should be made to your IBM Authorized Dealer or your IBM Marketing Representative.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Commercial Relations, IBM Corporation, Purchase, NY 10577.

COPYRIGHT LICENSE: This publication contains printed sample application programs in source language, which illustrate OS/2 programming techniques. You may copy and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the OS/2 application programming interface.

Each copy of any portion of these sample programs or any derivative work, which is distributed to others, must include a copyright notice as follows: "© (your company name) (year) All Rights Reserved."

© Copyright International Business Machines Corporation 1990. All rights reserved.

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Special Notices

The following terms, denoted by an asterisk (*) in this publication, are trademarks of the IBM Corporation in the United States and/or other countries:

IBM
Operating System/2
OS/2
Presentation Manager
Systems Application Architecture.

About This Book

This book, as well as the other books in the upgrade package, contains programming information that is new to or different from the information in the *IBM® Operating System/2® (OS/2®) Programming Tools and Information Version 1.2* library (part number 6024929). In addition, information from the *OS/2 Programming Tools and Information Version 1.2 Technical Update* (part number 64F1705) is included in this upgrade package.

The upgrade describes features added by the OS/2 Version 1.3 product, and amends some of the information that was published with OS/2 Version 1.2.

This book is a companion to the *Version 1.2 Dialog Tag Language Guide and Reference*. **Only those chapters of the Version 1.2 book that are changed by the Version 1.3 product are included herein.** The chapter numbers and titles are the same as those in the Version 1.2 book. As a convenience, the beginning of each chapter in this book provides a summary of changes for that chapter.

Who Should Read This Book

This book is for application designers and programmers who are using the components of the *IBM OS/2 Version 1.2/1.3 Programming Tools and Information Technical Upgrade* package. The reader is assumed to be familiar with the services of OS/2.

* Trademark of the IBM Corporation

Contents

Chapter 5. Application Panel Fields	1
Other Data Field Attributes	1
Data Columns	1
Defining Selection Lists	1
 Chapter 15. Tag Reference	3
ABC (Action Bar Choice)	3
CHOICE (Selection Choice)	3
DTACOL (Data Column)	4
DTAFLD (Data Field)	5
LSTCOL (List Column)	7
PDC (Pull-Down Choice)	8
SELCOL (Selection Column)	8
 Index	11

Chapter 5. Application Panel Fields

Summary of Changes

New	Updated	Section Title
	✓	Other Data Field Attributes
	✓	Data Columns
	✓	Defining Selection Lists

Other Data Field Attributes

On page 5-13, add the following attribute and description after the **AUTOCLR** attribute and description:

FONT

This attribute allows you to specify the font used for the entry field of the data field. If you specify **SYSTEM** as the font value, the system proportional font is used. If you specify **SYSMONO**, the system monospaced font is used. The default, **SYSTEM**, is used if no value is specified.

Data Columns

On page 5-24, add the following attribute and description after the **SELWIDTH** attribute and description:

FONT

Specifies the font used for the entry field of the data fields.

On page 5-24, add the following before the last paragraph:

The **FONT** attribute specifies the font used for the entry field of the data field. If you specify **SYSTEM** as the font value, the system proportional font is used. If you specify **SYSMONO**, the system monospaced font is used. The default, **SYSTEM**, is used if no value is specified.

Defining Selection Lists

On page 5-27, replace the next to the last paragraph on the page with the following:

In the preceding markup, the **SELLST** and **SELCOL** tags are used to define the selection list. To indicate the font type for the data displayed in the selection list, specify the **FONT** attribute on the **SELCON** tag. The two types of fonts are **SYSMON** or **SYSTEM** (the default).

Chapter 15. Tag Reference

Summary of Changes

New	Updated	Section Title
	✓	ABC (Action Bar Choice)
	✓	CHOICE (Selection Choice)
	✓	PDC (Pull-Down Choice)
	✓	DTACOL (Data Column)
	✓	DTAFLD (Data Field)
	✓	LSTCOL (List Column)
	✓	SELCOL (Selection Column)

ABC (Action Bar Choice)

On page 15-6, under **choice-description-text**, replace the first paragraph with the following:

This specifies the text that appears in the action bar. The text is limited to 80 bytes. You can use an M tag to identify a mnemonic character for the action bar choice.

CHOICE (Selection Choice)


On page 15-32, under **choice-description-text**, replace the first paragraph with the following:

This indicates the text of the choice item. The maximum length is limited to 80 bytes. If you use a mnemonic (M tag) within the *choice-description-text*, the mnemonic character is emphasized with an underscore at run time and provides fast path selection for keyboard users.

DTACOL (Data Column)

On page 15-58, replace the first six paragraphs (including the syntax diagram) with the following:

The DTACOL tag defines column widths for the data fields (DTAFLD) and selection fields (SELFLD) that are coded within a DTACOL tag.



FONT=SYSTEM | SYSMONO

This attribute allows you to specify the font to be used for the entry field text. Specifying SYSMONO causes the system monospaced font to be used. Specifying SYSTEM causes the proportional font to be used.

ENTWIDTH=n

The *entry-width* attribute specifies the width, in character units, of the data fields. The minimum width value is 1 and the maximum is 128. If any field defines the ENTWIDTH attribute, it overrides the value on this attribute.

Note: The ENTWIDTH attribute does not apply to nested selection fields.

PMTWIDTH=n

The *prompt-width* attribute sets the width, in character units, of the prompts for data fields and selection fields coded within the data column. The minimum width value is 0 and the maximum is 128. If the prompt text has fewer character units than the field allows, the Dialog Manager supplies blanks to fill the remaining spaces. If any prompt contains more character units than the width you specify, that prompt will be word-wrapped to fit on multiple lines. If any field defines the PMTWIDTH attribute, it overrides the values on this attribute.

DESWIDTH=n

The *description-width* attribute specifies the width, in character units, of the description text of the enclosed DTAFLDD tags. The minimum width value is 0 and the maximum is 128.

Note: That the DESWIDTH attribute does not apply to nested selection fields.

SELWIDTH=n


The *selection-width* attribute specifies the space to be taken up by the selection-width part of the enclosed selection fields. This is useful for getting the choices in the selection to occupy the same amount of space. The minimum width value is 1 and the maximum is 128. If you specify the SELWIDTH parameter on the SELFLD tag, it overrides the value of this attribute.

The selection part of a selection field includes either a check box or a radio button and the following text. For immediate-action selection fields, it includes the text and the surrounding pushbutton border.

DTAFLD (Data Field)

Replace pages 15-62 and 15-63, with the following:

The DTAFLD tag defines an input field, an output field or an input/output field.



NAME=field-name

Specifies the name of the field.

This name can be used:

- On the DISPLAY call to position a message pop-up window relative to the data field.
- On the ADDPOP call to position a pop-up window relative to the data field.
- On the DISPLAY call to place the cursor in the data field.
- On the PANEL definition to place the cursor in the data field.

The name must have the following characteristics:

- 1 – 8 characters in length.
- The first (or only) character must be A – Z or a – z.
- Remaining characters, if any, must be A – Z, a – z, or 0 – 9.

Lowercase characters are translated to their uppercase equivalents.

HELP=help-panel-name

This attribute assigns a name to a help panel the Dialog Manager displays when the user selects help for this data field. If the user selects help on a data field, the help defined for the data field displays. If no help is specified for the data field, the extended help panel displays. If an extended help panel was not defined, a message is displayed stating that no help is defined. This attribute is valid only when USAGE=IN or BOTH. The *help-panel-name* must have the following characteristics:

- 1–8 characters in length.
- The first (or only) character must be A–Z or a–z.
- Remaining characters, if any, must be A–Z, a–z, or 0–9.

Lowercase characters are translated to their uppercase equivalents.

DATAVAR=field-data

A variable name that specifies the data in the field. The value coded must be a variable-name without using % notation. The DATAVAR attribute must be a scalar variable.

The maximum length of a data value that can be displayed or entered (with possible scrolling) within a DATAFLD entry is determined by the characteristics of:

- The explicitly specified VARCLASS, (if any) or
- The default VARCLASS for the DATAVAR.

FONT=SYSTEM | SYSMONO

This attribute allows you to specify the font to be used for the entry field text. Specifying SYSMONO causes the system monospaced font to be used. Specifying SYSTEM causes the proportional font to be used.

VARCLASS=variable-class-name

This attribute specifies the name of the variable class, defined using the VARCLASS tag, that overrides the default variable class referenced by the VARDCL that declared the data variable for this field. The VARCLASS specified must have the TYPE information that matches the TYPE information of the VARCLASS overridden.

If the VARCLASS specified does not have TYPE information that matches the type information of the overridden VARCLASS, a warning message is issued.

USAGE=BOTH | IN | OUT

The USAGE attribute indicates whether the field is for input-only, output-only, or both.

An entry field is a field on a panel into which the user can enter data. An input-only field does not initially display the value of the variable associated with the field. BOTH (input/output) field, however, functions much like an input-only field but the current value of the DATAVAR is also displayed in the entry field when the panel is initially displayed. Input fields can only be one line, but may be horizontally scrollable.

An output-only field simply displays the current value of the variable associated with the field. If the text does not completely fit into the width of the output field, the output is word-wrapped to the next line until all of the text is displayed. An output-only field cannot contain the cursor.

REQUIRED=NO | YES

This attribute indicates if the field requires input. The default is NO. If you set both REQUIRED=YES and USAGE=OUT, the compiler issues a warning message and REQUIRED=YES is ignored. This attribute is valid only when USAGE=IN or BOTH.

MSG=message-identifier


The MSG attribute specifies the identifier for a message that the Dialog Manager displays when the user does not complete a required entry (required attribute). If you do not specify a *message-identifier*, the Dialog Manager uses a default message.

This attribute is valid only if REQUIRED=YES.

LSTCOL (List Column)

On page 15-105, replace the syntax diagram with the following:

The LSTCOL tag defines a column within a list field.



On page 15-106, replace the information under **ALIGN=START | END | CENTER** with the following:

ALIGN=START | END | CENTER

The ALIGN attribute specifies how the data value is to be displayed in the list field.

If you specify the START alignment, the value is left-justified in the field. If you specify the END alignment, the value is right-justified and if you specify the CENTER alignment, the value is centered.

Output fields are not scrollable: however, input fields may be scrollable as necessary.

FONT=SYSTEM | SYSMONO

This attribute allows you to specify the font to be used for the entry field text. Specifying SYSMONO causes the system monospaced font to be used. Specifying SYSTEM causes the proportional font to be used.

column-heading

The text used for the title of the column. The column heading is centered above each column independent of the value of the ALIGN attribute. If the column-heading width and the COLWIDTH values are not equal, the greater of the two is used. If the column heading and the COLWIDTH attributes are omitted, the size of the column variable determines the width.

PDC (Pull-Down Choice)


On page 15-146, under **pull-down-description-text**, replace the first paragraph with the following:

This indicates the text of the action bar choice pull-down. The maximum length of the text is 80 bytes.

SELCOL (Selection Column)

On page 15-158, replace the first four paragraphs (including the syntax diagram), with the following:

The SELCOL tag defines the array of column data where each element of the array corresponds to an item in the selection list.

**DATAVAR = column-variable**

The DATAVAR attribute specifies the name of the array variable that contains the items that are declared on the VARDCL tag.

FONT=SYSTEM | SYSMONO

This attribute allows you to specify the font to be used for the entry field text. Specifying SYSMONO causes the system monospaced font to be used. Specifying SYSTEM causes the proportional font to be used.

VARCLASS = variable-class-name

This attribute specifies the name of the variable class, defined using the VARCLASS tag. This variable class overrides the default variable class referenced by the VARDCL that declared the data variable for this column. The VARCLASS specified must have the TYPE information that matches the TYPE information of the VARCLASS overridden.

If the VARCLASS specified does not have TYPE information that matches the type information of the overridden VARCLASS, a warning message is issued.

Index

A

ABC tag 3
action bar choice tag 3

C

CHOICE tag 3

D

data column tag 4
data field tag 5
data fields, fonts for 1
DTACOL tag 4
DTAFLD tag 5

F

font attribute 1

L

list column tag 7
LSTCOL tag 7

P

PDC tag 8
pull-down choice tag 8

S

SELCOL tag 8
selection choice tag 3
selection column tag 8
SYSMON 1
SYSTEM 1

IBM United Kingdom
International Products Limited
PO Box 41, North Harbour
Portsmouth, PO6 3AU
England

Printed in Denmark by
J. H. Schultz Print a/s
Copenhagen

